

-----  
Securithor 1.1.x.x  
By MCDI  
-----

August 2010  
www.MCDI.COM / www. Securithor.com  
-----

Before you begin, please read the installation instruction in this file carefully.

You should have admin privileges to install Securithor.

## 1. Description

-----

SECURITHOR is a software automation product for alarm monitoring. This software package is intended but not limited to use in Central Monitoring Station, Housing complexes, Hospital Wards, Manufacturing plants or Control Rooms.

Designed by MCDI Security Products Inc. of Montreal Canada, it is the logical successor to SAMM and WinSAMM dating back to the 1990.

## 2. System Requirements

-----

This program runs under Windows XP/Vista/7.

## 3. File locations

-----

After installation the files will be copied by default in %Program Files%/MCDI folder.

## 4-Installation Instruction

-----  
-----

### 4.1 Securithor\_Patch1.1.x.x.exe

-----

This file is used to upgrade the previous version of Securithor.

How to install:

Stop Securithor if it is running.

Stop STnet if it is running.

Stop STReceiver if it is running.

Run Securithor\_Patch1.1.x.x.exe file.

A pop up message will be displayed asking if you want to clean up your database.

If your answer is yes, it will just update your database. IT WILL NOT DELETE IT.

#### 4.2 Securithor\_Installer.exe:

-----

##### NOTE:

..If you have previous version of Securithor installed on your PC and do not want to use Patch to upgrade it:

....Stop Securithor if it is running.

....Stop STnet if it is running.

....Uninstall previous version of Securithor.

Run Securithor\_Installer.exe file, select your language and follow the instructions.

This installation can be done on the server and the station PCs.

All the files are copied into the %Program Files%/MCDI folder and required shortcuts are created on your desktop.

-----

#### 4.3 STImporter.exe

Contact MCDI to inquire about SAMM/WinSAMM to SECURITHOR upgrade. Upgrade is part of support plans.

**A VALID SECURITHOR LICENSE MUST BE PURCHASED TO CONVERT WINSAMM TO SECURITHOR.**

#### 5. How to set up and Run Securithor for the first time:

-----

-----

SECURITHOR's installer is common to the single station version ST1 and the Network Edition STnet.

##### 5.1 on a single station

-----

On the single station, the server is considered as "localhost" by default.

Remove settings.ini file in the Securithor folder if it exists.

Start Securithor on the PC and login with operator # "1" and password "securithor" ( We assume you run Securithor on the same PC where your database is located).

At the first login attempt, it will give you a message that STnet is not running. Give a few moments to the application to start STnet.

On STnet window, the IP of the server is set to local host, press connect. A popup message will be displayed if you want to add STnet to start up menu. If you answer yes, the STnet will be added to start up menu and you do not need to start it every time. You can add this file to start up at any time by selecting StartUp/ON menu.

Log IN Securithor.

## 5.2 On network stations

-----

On the Server PC (where your database is located), run Netconfig.exe file (exists in %ProgramFiles% / MCDI/Securithor folder).

Select network radio button. Two Server descriptions are already in the list; local host and 127.0.0.0.

A message with default IP address of your network will popup (ex. 192.168.x.x). Accepting the option will allow all the PCs running Securithor in your network to connect to the server.

You can also specify the IP addresses of each PC to give (the) access to the particular connections.

Save the entries and close NetConfig.

Run STnet on the server machine.

On STnet window, enter "localhost" as IP in the IPAddress box and press connect.

A popup message will be displayed if you want to add STnet to start up menu.

By selecting 'yes', STnet will be added to start up menu and you do not need to start it every time. You can add this file to start up at any time by selecting StartUp/ON menu.

Start Securithor on each PC.

Before login, go to Setting > Network and enter the server IP address and close Setting window.

When you login, if STnet is not running on the server, it will give you a message that STnet is not running on the server.  
Run STnet on the server and try to login again.

Note: If STnet is not located on the same machine as server, then instead of "localhost", you should enter the IP address of the server.

For more info, please read the User Guide in Securithor folder or [www.securithor.com/userguide](http://www.securithor.com/userguide).

## 6. Licensing

-----

By default, you have 30 days demo licensing. If for any reason you need to update the license file, send HIDnw file stored in Securithor folder to [support@mcdi.com](mailto:support@mcdi.com) or contact your dealer to create a license file.

The license file format is "xxxxx-xxxxxx ST1.license" and it should be stored in the same folder where STnet is located.

Note: For workstations, you do not need individual license. The number of workstations is included in the license of the server.

## 7. Contact Info

-----

For more support:

By phone:

French or English: +514-481-1067

**Linea directa en espanol: +514-487-0441:**

By email: [support@mcdi.com](mailto:support@mcdi.com)

For more information regarding support, please check our website:

<http://mcdi.com/an/contacts.htm>

Also see the FAQ available at

<http://securithor.com/>